




From the **Map Dashboard**, click the **Landmarks** menu item to open the Landmarks tab. All of your landmarks are listed on this tab.



When you click on a landmark from the list or when you click on a landmark from the map, the **Landmark Card** appears, which shows you the radius and latitude / longitude.



**Note.** “Help! Why can’t I see my landmarks on the map?” Ensure the **Landmarks toggle** is turned on from the Map Toolbar:  or from the Landmark Card:  **Toggle**.

The boundary that you set up for a landmark can exist as a circle or a polygon.

- **Circle** – The default shape for a landmark boundary is a circle. The default radius is determined by your current zoom level. Circle landmarks are typically sufficient for most tasks (i.e., report labels, map filters, turn-by-turn directions, and so on).
- **Polygon** – Polygons allow you to define a more precise boundary by tracing an outline around a specific area (up to 256 vertices). Polygon landmarks are more often used when the exclusion or inclusion of specific perimeters is important, such as when sending alerts when a vehicle enters or exits a specific location.

## Adding a Landmark

You can add a landmark by drawing a new one from the Landmarks tab or from a dropped pin on the map.

### Draw a New Landmark

Drawing a landmark allows you to visually specify the borders on the map surface.

#### ► To draw a new landmark:

1. From the menu, click **Landmarks**.
2. Click **Add Landmark**.

A default circle appears on the center of the map. The circle has four sizing handles on the perimeter and one moving handle in the center.

1. Enter a label for the landmark.
2. Choose the shape of the landmark (Circle or Polygon):

- **Circle** – Re-size the radius by dragging-and-dropping one of the four sizing handles on the perimeter. (Alternatively, you can enter a custom radius in feet, miles, meters, or kilometers.) Move the circle by dragging-and-dropping the moving node. (Alternatively, you can enter a custom Lat/Lng.)
- **Polygon** – Click on the map to start drawing a polygon shape. Drag and drop the sizing handles as needed.

1. Choose a Color.
2. Select an **attribute**, if applicable.”




**Note.** Colors can help you categorize or group landmarks (e.g., set all customer sites to light orange).

1. Click **Save**.

## Create a Landmark from a Pin

A dropped pin marks a temporary location based on a visual reference or an address/lat/lon. Creating a landmark from a dropped pin allows you to reuse that location again.

#### ► To create a landmark from a pin:

1. From the Map Toolbar, click **Drop a Pin** ()
2. Drag-and-drop the pin to the location from which you want to create a landmark.
3. Click **Landmark**.

A default circle appears on the center of the map. The circle has four sizing handles on the perimeter and one moving handle in the center.

1. Enter a label for the landmark.
2. Choose the shape of the landmark (Circle or Polygon):
  - **Circle** – Re-size the radius by dragging-and-dropping one of the four sizing handles on the perimeter. (Alternatively, you can enter a custom radius in feet, miles, meters, or kilometers.) Move the circle by dragging-and-dropping the moving node. (Alternatively, you can enter a custom Lat/Lng.)
  - **Polygon** – Click on the map to start drawing a polygon shape. Drag and drop the sizing handles as needed.

1. Choose a Color.



**Note.** Colors can help you categorize or group landmarks (e.g., set all customer sites to light orange).

1. Click **Save**.

## Editing a Landmark

You can edit landmark details or delete landmarks.

### Edit Landmark Details

Any properties that you edit on the landmark will be reflected the next time you run a report or alert that uses that landmark.

#### ► To edit a landmark:

1. From the map, Search Results tab, or Landmarks tab, click the landmark that you want to edit.
2. From the Landmark Card, click **Edit**.
3. The following fields are available to modify:

Field Name	Description
Label	The name of the landmark.
Circle / Polygon	The shape of the landmark.
Color	The color used on the map to denote the landmark.
Lat/Lng	The latitude and longitude coordinates.
Radius	The distance from the center to the perimeter of the landmark.
Attribute	The descriptive property associated with the landmark.

1. Click **Save**.

## Delete a Landmark



When you delete a landmark, any alerts that use the landmark will be updated to instead use all landmarks.

### ► To delete a landmark:

1. From the map, Search Results tab, or Landmarks tab, click the landmark that you want to delete.
2. From the Landmark Card, click **Delete**.
3. In the Delete Landmark pop-up window, click **OK**.

## Using Landmark Groups

Landmark groups are used to organize your landmarks based on logical or geographical separations that make sense to your business. In the context of the Map Dashboard, landmark groups allow you to temporarily hide (

 **Toggle** ) or center (  **Center** ) the map around a subset of landmarks.


## Create a Landmark Group







Creating a landmark group from the Map Dashboard allows you to choose the name of the group and the landmarks that belong in the group. For more landmark management options, visit the [Landmark Groups](#) or [Mass Update](#) administration pages.

### ► To add a new landmark group:

1. From the menu, click **Landmarks**.
2. Click **Create Group**.

3. Enter a name for the landmark group, and then select the check box next to each landmark you want to include in the group.



Editing Landmark Group	
 Save	
<input type="text" value="Customer Sites"/>	
<input type="checkbox"/>	
<input type="checkbox"/>	 000MB
<input type="checkbox"/>	 1 Trace Tracking
<input checked="" type="checkbox"/>	 101 202
<input checked="" type="checkbox"/>	 101 maker

1. Click **Save**.

## Add a Landmark to an Existing Group

If you want additional administration options for editing landmarks, visit the [Landmark Groups](#) administration page.

### ► To add a landmark to group:

1. From the menu, click **Landmarks**.
2. Click the target landmark group, and then click **Edit**.
3. Select the check box next to the landmark(s) you want to include in the group, and click **Save**.